

DATA MASTER CHANGE LOG

2022-08-29

Client: 2022.10

Data:

New features:

- Added a possibility to exclude/include all laps in the log

Improvements:

- Channels with no data logged can be hidden in the channel select window
- Cl.timeSlip calculation algorithm improved to avoid artefacts at the end of the lap
- Default aliases can be edited - not compatible with previous versions
- Channel properties (colour, filtering etc.) are saved in the project file

Fixes:

- Fixed stability issue causing random crashes of video
- Fixed an issue with video randomly freezing in slow motion
- Fixed issues with min/max limits of EMU Black/Classic channels

Changes:

- User-defined aliases created in previous versions will not be supported
- Added more default aliases

Visualizations:

New features:

- Added a possibility to overlay data over video – 2 layouts currently supported

2022-06-29

Client: 2022.8

Data:

New features:

- Added support of EMU Classic log files (.emulog, .bgc)
- .dmproj and .dmarchive files can be opened directly from the desktop

Improvements:

- After successfully packaging a project, a message box is displayed

Fixes:

- Fixed no offset bug when loading multiple files from EMU Black
- Fixed issue with longer drag runs not splitting correctly

- Fixed issue with math channel frequencies not saving properly
- Fixed bug when starting lap is not equal 0
- Fixed bug with math channels freezing

Changes:

- Laps generated from the reference track can't be split/deleted
- File description changed to DATA_MASTER

Visualizations:

New features:

- The Channel Report panel added
- Added a text box showing the current offset in the Video panel (manual synchronization mode)

Improvements:

- A grid can be toggled in the Graph Log
- Added shortcut to toggle between time and distance axis
- By clicking the segment label you can focus on segment in the Graph Log
- When comparing laps, the channel filtering remains active in the Graph Log
- Button labels in manual synchronization changed

Fixes:

- Fixed issue with filtering alias channels in the Graph Log
- Fixed issue with the cursor not updating when scrolling in the Graph Log